

MagicInfoAuthor for Samsung Signage Devices

Here is a short guide how to use Digitalsignagepress with Samsung Signage devices.

- 1. Download and install MagicInfo Author software.
 - <u>https://digitalsignagepress.com/Download/MagicInfoAuthor.exe</u>
- 2. Open the MagicInfo Author Software
- 3. Choose File \rightarrow New Content

🛷 мас	JICINIO AUTNOI										
Datei(<u>F</u>) Bearbeiten(<u>E</u>)										
	Neuer Inhalt(<u>N</u>)		Ctrl+N	Xe	à 🖺 🏠 • 🗉				中山	ΠE	₩ 🗄
				2 3		TT			T T	· T·	T · ab
				Data.							
Ξ					-						
2	Speichern unter(<u>A</u>)										
\mathbf{b}											
1	Veröffentlichen(P)										
	Beenden(<u>X</u>)										
				Zeits	trahl	Seitenverlau	ſ				

4. Choose your Playertype (e.g. S1, S2 ...)

	Inhaltseinstellung - Normale Inhalte						
Zeitstrahl	Bezeichnung des Inhaltes Vicht dofmert Player-Typ i løger Datei für Hintergrundmusk Anzeigeoption Sz Payer Auflösung SJ Payer Breite APayer Höhe 1080 PHIt Assistent erstellen Erstellen Abbrechen						



- 5. Add the Web Element into the template
 - Click on Elements
 - Choose "Other" in the drop down menu
 - · Copy the Web Element into your template on the left side



6. Set the Displayduration to 23:59:59:59







7. Set the Height and Width to 1920x1080 and Position X and Y to 0

8. Enter your URL



9. Save the file and copy it onto an USB stick



! If you already have your TV configured with the Playertype "MagicInfo" you can skip step 10 !

- 10. Factory reset and installation wizard
 - Power off the TV
 - press Mute 1 8 2 Power on your remote
 - choose "option" → "factory reset"
 - At step 6 of the installation wizard choose "MagicInfo"
- 11. Copy LFD file onto the TV
 - put the USB stick into the TV
 - press "Home" on your remote
 - choose Playertype
 - navigate into the upper right corner and click on options
 - click on send
 - choose the file from the USB stick which should be copied
 - click on send again
 - choose internal
 - click on start
 - after the file has been send, click on cancel
 - you can remove the USB stick now

12. Open the File

• the file is now located in the folder "Own Templates"